

**Ansilove**

<b>REVISION HISTORY</b>
-------------------------

NUMBER	DATE	DESCRIPTION	NAME
1.11	2014-03-26		FC

---

## Contents

<b>1</b>	<b>Description</b>	<b>1</b>
1.1	Features	1
1.2	Supported charsets	1
1.3	Supported unofficial charsets	2
<b>2</b>	<b>Requirements</b>	<b>2</b>
<b>3</b>	<b>Installation</b>	<b>2</b>
3.1	Using tarballs	2
3.2	Using Git	2
<b>4</b>	<b>Configuration options</b>	<b>2</b>
4.1	Options list	3
<b>5</b>	<b>Supported options for each file format</b>	<b>4</b>
<b>6</b>	<b>Command line converter</b>	<b>4</b>
6.1	Usage	5
6.2	Columns options	5
6.3	Font options	5
6.3.1	Amiga fonts options	5
6.3.2	PC fonts options	6
6.4	Bits options	6
6.5	iCE colors options	7
6.6	Examples	7
<b>7</b>	<b>Library usage for doing on the fly conversions on web pages</b>	<b>8</b>
7.1	Including custom image tags in HTML code	9
<b>8</b>	<b>Library usage</b>	<b>10</b>
8.1	Loading <i>ansilove.php</i> library in your PHP source	10
8.2	Calling the adequate loaders to convert input files	10
<b>9</b>	<b>Retrieve SAUCE Informations</b>	<b>10</b>
9.1	Loading <i>ansilove.php</i> library in your PHP source	10
9.2	Loading sauce informations	10
<b>10</b>	<b>License</b>	<b>11</b>
<b>11</b>	<b>Distribution</b>	<b>12</b>

---

---

<b>12 Support and Donations</b>	<b>12</b>
<b>13 Author</b>	<b>12</b>
<b>14 Contact</b>	<b>12</b>

---

## 1 Description

**Ansilove** is a set of tools to convert ANSi and artscene-related file formats into **PNG** images, supporting **ANSi** (.ANS), **PCBOARD** (.PCB), **BiNARY** (.BIN), **ADF** (.ADF), **iDF** (.IDF), **TUNDRA** (.TND) and **XBiN** (.XB) formats.

It includes an all purposes **command line converter**, along with a **library** to use on web pages for doing "**on the fly**" conversions. It creates size optimized **4-bit PNG** files and supports **SAUCE** (Standard Architecture for Universal Comment Extentions), 80x25 and 80x50 PC fonts (including all the 14 **MS-DOS charsets** and some unofficial ones), Amiga fonts, and iCE colors.

It is written in **PHP**, and can thus be run on any supported system : the command line converter can be used under **Linux**, **Mac OS X**, **Windows**, and so far and so on.



### Important

Ansilove doesn't require any Web server : you can use the bundled command line converter to convert files locally on your computer.

---

### 1.1 Features

- ANSi (.ANS) format support
- PCBOARD (.PCB) format support
- BiNARY (.BIN) format support
- ADF (.ADF) format support (Artworx)
- iDF (.IDF) format support (iCE Draw)
- TUNDRA (.TND) format support - <http://tundradraw.sourceforge.net>
- XBiN (.XB) format support - <http://www.acid.org/info/xbin/xbin.htm>
- Small output file size (4-bit PNG)
- SAUCE (Standard Architecture for Universal Comment Extentions)
- 80x25 font support
- 80x50 font support
- Amiga font support
- iCE colors support

### 1.2 Supported charsets

- IBM PC (Code page 437)
  - Baltic (Code page 775)
  - Cyrillic (Code page 855)
  - French Canadian (Code page 863)
  - Greek (Code pages 737 and 869)
  - Hebrew (Code page 862)
  - Icelandic (Code page 861)
-

- Latin-1 (Code page 850)
- Latin-2 (Code page 852)
- Nordic (Code page 865)
- Portuguese (Code page 860)
- Russian (Code page 866)
- Turkish (Code page 857)

### 1.3 Supported unofficial charsets

- Armenian
- Persian (Iran System encoding standard)

## 2 Requirements

**Ansilove** requires *PHP* with the *GD* module installed. If you want to convert huge files, you may have to increase the *memory\_limit* size in your *php.ini* file.

## 3 Installation

### 3.1 Using tarballs

```
wget http://downloads.sourceforge.net/project/ansilove/ansilove-php/1.11/ansilove-php-1.11. tar.gz  
tar xvfz ansilove-php-1.11.tar.gz
```

### 3.2 Using Git

```
git clone git@github.com:fcambus/ansilove.git
```



#### Important

Under Windows people must install the PHP binaries : the easiest way is to use the *.exe* installer and enable the GD library.

## 4 Configuration options

The configuration options are defined in the *ansilove.cfg.php* file.

## 4.1 Options list

- ANSILOVE\_FILES\_DIRECTORY

Defines the directory where all the files to be rendered must be placed when using the library online to do "on the fly" conversions. Default value : *ansis/*

- ANSILOVE\_LOG\_FILE

Defines the log file used by the error message logger. Default value : *ansilove.log*

- PCBOARD\_STRIP\_CODES

Defines a serie of comma separated values containing PCBoard codes to be stripped from the output.  
Default value : "@POFF@,@WAIT@", which means all @POFF@ and @WAIT@ codes will be stripped.

- DIZ\_EXTENSIONS

Defines a serie of comma separated values specifying which files to render in DIZ mode. Default value : ".diz,.ion"

- SUBSTITUTE\_BREAK

Whether or not stop rendering input files when the substitute (SUB) character is encountered. Default value : *1 (ENABLED)*

- WRAP\_COLUMN\_80

Whether or not enable 80th column wrapping. Default value : *1 (ENABLED)*

- CED\_BACKGROUND\_COLOR

Defines RGB values of the CED mode background color.

- CED\_FOREGROUND\_COLOR

Defines RGB values of the CED mode foreground color.

- WORKBENCH\_COLOR

Defines RGB values of the WorkBench mode colors.

- THUMBNAILS\_SIZE

Defines thumbnails size multiplicator. Default value : *1* (will produce 80 pixels width output)

- THUMBNAIS\_HEIGHT

Defines maximum thumbnails height (in pixels). Default value : *0* (will produce full height output)

- THUMBNAIS\_TAG

Defines the tag added to the output file name. Default value : *-thumbnail*

- SPLIT

Whether or not split output in multiple images files. Default value : *0 (DISABLED)*

- SPLIT\_HEIGHT

Define the height (in pixels) of each splitted pictures. Default value : *4096*

- SPLIT\_SEPARATOR

Defines the separator used in output file names. Default value : *.*

## 5 Supported options for each file format

Format	columns	font	bits	icecolors
ANS		X	X	X
PCB		X	X	X
BIN	X	X	X	X
ADF				
IDF				
TND		X	X	
XB				

## 6 Command line converter

The command line converter can be invoked by typing :

```
./ansilove
```

### Note

Windows users should use the bundled *ansilove.bat* file.



**Caution**

Check the file header to ensure the path of your PHP interpreter is correct : Ansilove uses /usr/bin/php as default.

## 6.1 Usage

```
ansilove inputfile columns font bits icecolors
```

**Note**

If no options are specified, default settings are used : 80x25, 8-bit font and iCE colors turned off. If no columns are specified for .BIN, default value is 160.

## 6.2 Columns options

**Important**

Used for .BIN files only. Skip this option when converting other formats.

## 6.3 Font options

- 80x25
- 80x50
- PC or Amiga fonts (8-bit font only)

### 6.3.1 Amiga fonts options

- amiga (alias to Topaz)
- b-strict (Original B-Strict font)
- b-struct (Original B-Struct font)
- microknight (Original MicroKnight version)
- microknight+ (Modified MicroKnight version)
- microknightplus (alias to MicroKnight + to be used in URLs)
- mosoul (Original mO'sOul font)
- pot-noodle (Original P0T-NOoDLE font)
- topaz (Original Topaz Kickstart 2.x version)
- topaz+ (Modified Topaz Kickstart 2.x+ version)
- topazplus (alias to Topaz+ to be used in URLs)
- topaz500 (Original Topaz Kickstart 1.x version)

- topaz500+ (Modified Topaz Kickstart 1.x version)
- topaz500plus (alias to Topaz500+ to be used in URLs)

---

**Note**

All the amiga fonts come from the excellent [Amiga bitmap fonts](#) package by dMG.

---

### 6.3.2 PC fonts options

- 80x25 (Default, code page 437)
- 80x50 (Code page 437, 80x50 mode)
- armenian
- baltic (Code page 775)
- cyrillic (Code page 855)
- french-canadian (Code page 863)
- greek (Code page 737)
- greek-869 (Code page 869)
- hebrew (Code page 862)
- icelandic (Code page 861)
- latin1 (Code page 850)
- latin2 (Code page 852)
- nordic (Code page 865)
- persian (Iran System encoding standard)
- portuguese (Code page 860)
- russian (Code page 866)
- terminus (Terminus font)
- turkish (Code page 857)

## 6.4 Bits options

- 8 (8-bit)

Default rendering mode.

- 9 (9-bit)

Renders the 9th column of block characters, causing the output to look like it's displayed in real textmode.

- ced
-

Renders files in black on gray, and limit the output to 78 columns (only available in ANSi loader).

Used together with an Amiga font, the output will look like it is displayed on Amiga.

---

**Note**

It is possible to set custom RGB values by modifying the predefined constants *CED\_BACKGROUND\_COLOR* and *CED\_FOREGROUND\_COLOR* in the configuration file.

---

- thumbnail

Generate thumbnail, using the full length picture by default.

---

**Note**

You can adjust the maximum height and the output size by changing the *THUMBNAILS\_HEIGHT* and *THUMBNAILS\_SIZE* options in the configuration file. NOTE: It is also possible to change the tag added to the output file name by changing the *THUMBNAILS\_TAG* option in the configuration file.

---

- transparent

Renders files with transparent background (only available in ANSi loader).

- workbench

Renders files using Amiga Workbench colors (only available in ANSi loader).

---

**Note**

It is possible to set custom RGB values by modifying the predefined constants *WORKBENCH\_COLOR* in the configuration file.

---

## 6.5 iCE colors options

- 0 (turned **OFF**)
- 1 (turned **ON**)

## 6.6 Examples

```
ansilove ansi.ans
ansilove ansi.ans 80x25 9 (80x25 font, 9-bit)
ansilove ansi.ans 80x25 thumbnail (80x25 font, thumbnail rendering)
ansilove ansi.ans 80x50 9 (80x50 font, 9-bit)
ansilove ansi.ans russian 9 (Russian font, 9-bit)
ansilove ansi.ans amiga (Amiga font)
```

---

```
ansilove pcbboard.pcb
ansilove pcbboard.pcb 80x25 9 (80x25 font, 9-bit)
ansilove pcbboard.pcb 80x25 thumbnail (80x25 font, thumbnail rendering)
```

```
ansilove binary.bin 160
ansilove binary.bin 160 80x25 9 (80x25 font, 9-bit)
ansilove binary.bin 160 80x25 thumbnail (80x25 font, thumbnail rendering)
ansilove binary.bin 160 80x50 9 (80x50 font, 9-bit)
```

```
ansilove adf.adf
ansilove adf.adf thumbnail (thumbnail rendering)
```

```
ansilove idf.idf
ansilove idf.idf thumbnail (thumbnail rendering)
```

```
ansilove tundra.tnd
ansilove tundra.tnd 80x25 9 (80x25 font, 9-bit)
ansilove tundra.tnd 80x25 thumbnail (80x25 font, thumbnail rendering)
```

```
ansilove xbin.xb
ansilove xbin.xb thumbnail (thumbnail rendering)
```

**Important**

Files with a .DIZ extension are rendered with the exact needed number of columns. White spaces and empty lines at the beginning and end of DIZ files are stripped from the output.

**Note**

You can customize file extensions definitions in the configuration file by modifying the predefined constant called `DIZ_EXTENSIONS`

## 7 Library usage for doing on the fly conversions on web pages

Using Ansilove library for doing "on the fly" conversions on Web pages, can be done using these loaders :

- `load_ansi.php`
- `load_pcbboard.php`
- `load_bin.php`
- `load_adf.php`
- `load_idf.php`
- `load_tundra.php`
- `load_xbin.php`

Upload the loaders you plan to use, the library *ansilove.php*, the config file *ansilove.cfg.php*, along with the *fonts* directory somewhere on your web site.

For security issues, all the files to be rendered must be placed in a directory, which is *ansis/* by default (the ending slash is required). This value is defined in the configuration file by the `ANSILOVE_FILES_DIRECTORY` constant.

**Caution**

Do **NOT** unset the `ANSILOVE_FILES_DIRECTORY` constant, else it'll be possible to convert files laying in the same directory than the loaders, which could lead to possible security leaks.

**Important**

Please note that the input is sanitized, so it is impossible to use `/` and `..` in paths.

## 7.1 Including custom image tags in HTML code

```








```

```








```

```





```

```


```

```


```

```



```

```


```

**Tip**

Check <examples/ansilove.html> to see the library in action.

---

**Note**

If you want your HTML code to validate correctly, you should replace the & characters by *&amp;* and add an *alt* element to the *img* tags.

---

## 8 Library usage

It is also possible to use the library in your PHP applications or scripts :

### 8.1 Loading *ansilove.php* library in your PHP source

```
require_once('ansilove.php');
```

### 8.2 Calling the adequate loaders to convert input files

```
load_ansi($input,$output,$font,$bits,$icecolors);
```

```
load_pcboard($input,$output,$font,$bits,$icecolors);
```

```
load_binary($input,$output,$columns,$font,$bits,$icecolors);
```

```
load_adf($input,$output);
```

```
load_idf($input,$output);
```

```
load_tundra($input,$output,$font,$bits);
```

```
load_xbin($input,$output);
```

## 9 Retrieve SAUCE Informations

Retrieving SAUCE informations from files can be done using the *load\_sauce* function :

### 9.1 Loading *ansilove.php* library in your PHP source

```
require_once('ansilove.php');
```

### 9.2 Loading sauce informations

```
$sauce=load_sauce($input_file_name);
```

The *load\_sauce* function will return an array containing the SAUCE informations :

---

```
Array
(
    [ID] => SAUCE
    [Version] => 00
    [Title] => Title
    [Author] => Author
    [Group] => Group
    [Date] => 19970621
    [FileSize] => 1997
    [DataType] => 1
    [FileType] => 1
    [TInfo1] => 80
    [TInfo2] => 29
    [TInfo3] => 0
    [TInfo4] => 0
    [Comments] => 10
    [Flags] => 0
    [Filler] =>
    [Comment_Line_01] => Comment Line
    [...]
    [Comment_Line_255] => Comment Line
)
```

---

**Note**

You can find detailed informations about SAUCE (including full specifications) here : <http://www.acid.org/info/sauce/sauce.htm>

---

## 10 License

Ansilove is released under a MIT-style license. See *LICENSE* file for details.

```
Copyright (c) 2003-2014, Frederic Cambus
Ansilove™ is a trademark of Frederic Cambus.
http://ansilove.sourceforge.net
All rights reserved.
```

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction except as noted below, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sublicense, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

- The Software and/or source code cannot be copied in whole and sold without meaningful modification for a profit.
- The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.
- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR

---

IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

## 11 Distribution

If you want to add an Ansilove download link on your page, please use the following download link :

<http://sourceforge.net/projects/ansilove/files/>

Ansilove is now also available on GitHub :

<https://github.com/fcambus/ansilove>

## 12 Support and Donations

Ansilove is the result of countless hours of coding and testing, in order to provide the most accurate possible **ANSi** and **ASCii** conversion tool. If you find this program useful, please consider making a donation, thank you <3

## 13 Author

Ansilove is developed by Frederic Cambus

Site : <http://www.cambus.net>

Twitter : <http://twitter.com/fcambus>

## 14 Contact

Project Homepage : <http://ansilove.sourceforge.net>

Sister project : <http://www.ascii-codes.com>

For bug report, feedback, or any other reasons, please write at the following address :

Frederic Cambus <fcambus AT users DOT sourceforge DOT net>